

## Radiography in Endodontics:

There are many applications of radiographs in endodontics including:

- 1) Aid in the diagnosis and localization of hard tissue alteration of the tooth (sclerosis and resorption) and periradicular structures
- 2) Determine the number, location, size, shape and direction of roots and root canals.
- 3) Estimate and confirm the length of root canals prior to instrumentation.
- 4) Determine the relative position of structures in facial or lingual dimensions.
- 5) Confirm the position and adaptation of the filling points.
- 6) Assess the outcome of root canal treatment.

### Working Length Determination of Teeth

Determination of an accurate working length is one of the most critical steps of endodontic therapy. The cleaning, shaping and obturation of the root canal system cannot be accomplished accurately unless working length is determined precisely. According to endodontic glossary working length is defined as the distance from a coronal reference point to a point at which canal preparation and obturation should terminate

### Objective of the Working Length

To establish the length of the tooth at which the canal preparation and subsequent obturation are to be completed. The apical end of the root canal is the CDJ, which is usually 0.5-1mm short of the radiographic apex. Sometimes the apical foramen is laterally positioned so it would be more than 1 mm from the radiographic apex.


	Maxillary	Mandibular
Central incisor	22.5	20.7
Lateral incisor	22.0	21.1
Canine	26.5	25.6
First premolar	20.6	21.6
Second premolar	21.5	22.3
First molar	20.8	21.0
Second molar	20.0	19.8

*From Black<sup>2</sup>*

### Reference point:


It is the site on the incisal edge or occlusal surface from which measurements are made. Usually it's the highest point on the incisal edge in anterior teeth & the tip of the cusp in posterior teeth. It should be:

- 1) Stable.
- 2) Easily visualized during preparation.
- 3) Not changing during or between appointments.



Before we discuss various methods of determination of working length, we need to understand the anatomic consideration regarding it.

1. Anatomic apex is "tip or end of root determined morphologically".
2. Radiographic apex is "tip or end of root determined radiographically".
3. Apical foramen is main apical opening of the root canal which may be located away from anatomic or radiographic apex.
4. Apical constriction (minor apical diameter) is apical portion of root canal having narrowest diameter. It is usually 0.5 -1 mm short of apical foramen. The minor diameter widens apically to foramen, i.e. major diameter.
5. Cementodentinal junction is the region where cementum and dentin are united, the point at which cemental surface terminates at or near the apex of tooth. It is not always necessary that CDJ always coincide with apical constriction. Location of CDJ ranges from 0.5 - 3 mm short of anatomic apex.



### Consequences of over-extended working length.

- Perforation through apical constriction.
- Over instrumentation.
- Overfilling of root canal.
- Increased incidence of postoperative pain.
- Prolonged healing period.
- Lower success rate due to incomplete regeneration of cementum, periodontal ligament and alveolar bone.

### Consequences of working short of actual working length.

- Incomplete cleaning and instrumentation of the canal.
- Persistent discomfort due to presence of pulpal remnants.
- Underfilling of the root canal.
- Incomplete apical seal.
- Apical leakage which supports existence of viable bacteria, this further leads to poor healing and periradicular lesion.

## **DIFFERENT METHODS OF WORKING LENGTH DETERMINATION**

Various methods for determining working length include using average root lengths from anatomic studies, preoperative radiographs, tactile sensation, etc. Other common methods include use of paper point, working length radiograph, electronic apex locators or any combination of the above.

### **1. RADIOGRAPHIC METHOD OF WORKING LENGTH DETERMINATION**

Procedure of Working Length determination

- 1- Examine preoperative radiograph & estimate the length of the tooth.
- 2- Know the average length of each tooth.
- 3- Place the file selected to be the correct initial width into the canal with its rubber stopper set at the estimated working length.
- 4- Radiograph the tooth to verify the position of the instrument.
- 5- Readjust the file length according to the radiograph result.

Results are fit, too long, or too short.

Notes:

- ❖ Bisecting technique in x-ray can't measure the exact length of the tooth. The parallel technique is more accurate
- ❖ The radiographs should be repeated in the following stages of treatment to check the working length.
- ❖ Initial size: It is the first instrument used to fit the working length & has slight resistance.
- ❖ If the radiograph results are too long e.g. 3mm. long, here we have to subtract 4 mm. & take another radiograph.
- ❖ If the radiograph results are too short e.g. 3mm. short, here we have to add 2mm. & then take another radiograph.

**When two superimposed canals are present (for example buccal and palatal canals of maxillary premolar, mesial canals of mandibular molar)**

One should take following steps:

- a) Take two individual radiographs with instrument placed in each canal.
- b) Take radiograph at different angulations, usually 20° to 40° at horizontal angulation.
- c) Insert two different instruments, e.g. K file in one canal, H file/ reamer in other canal and take radiograph at different angulations.

- d) Apply SLOB rule, that is expose tooth from mesial or distal horizontal angle, canal which moves to **same** direction, is **Lingual** whereas canal which moves to **Opposite** direction is **Buccal**.

## **2. ELECTRONIC APEX LOCATORS**

Radiographs are often misinterpreted because of difficulty in distinguishing the radicular anatomy and pathosis from normal structures. Electronic apex locators (EAL) are used for determining working length as an adjunct to radiography. They are basically used to locate the apical constriction or cementodentinal junction or the apical foramen, and not the radiographic apex.