
## Prosthodontic Vertical relation


**Vertical relation:** It is the amount of separation between the maxilla and the mandible in a frontal plane.

**Vertical dimension:** It is the distance between two selected points, one on a fixed and one on a movable member.

In general, the vertical measurement of face could be recorded between any two arbitrary selected points which are usually located one above the mouth (*at the tip of nose*) and the other below the mouth (*at the tip of chin in the mid line region*).



**Physiological rest position:** It is the postural position of the mandible when an individual is resting comfortably in an upright position and the associated muscles are in a state of minimal contractual activity.




Lecture 10	Prosthodontic	دبهاء الانصاري
<b>Rest vertical dimension:</b> It is the distance between two selected		
points (one at the tip of nose and the other at the tip of chin in		
the mid line region)	measured when th	e mandible is in the
physiologic rest position.		

**Occlusal vertical dimension:** It is the distance measured between two points when the occluding members (teeth or occlusal rims) are in contact.

**Interocclusal distance (interocclusal gap):** It is the distance between the occluding surfaces of the maxillary and mandibular teeth when the mandible is in a specified position.

**Interocclusal rest space (freeway space):** It is the distance between the occluding surface of maxillary and mandibular teeth when the mandible is in its physiological rest position. It is the difference between the vertical dimension of rest and the vertical dimension of occlusion.



#### **RVD** – **OVD** = Freeway space *normally* ≈ (2-4 mm)

Prosthodontic

**Importance of vertical dimension:** 

### **1. Functional roles:** includes:

a. Mastication. b. Deglutition. c. Phonetics. d. Respiration.

2. **Physiological role:** by maintenance health of tissue (mucosa, bone, muscles, and TMJ); also called **Comfortable role**.

### **3. Esthetic role. 4. Psychological role.**

## **Consequences of Increased vertical dimension:**

1. Increased trauma to the denture bearing area (acceleration of residual ridge resorption).

2.Inharmonious facial proportion (increased lower facial height).

- 3. Difficulty in swallowing and speech
- 4. Pain and clicking in the TMJ and muscular fatigue.
- 5. Stretching of the facial muscles and skin.
- 6. Increase space of the oral cavity.
- 7. Loss of biting power.
- 8. Increase naso-labial angle.
- 9. Sensation of bulky denture.
- 10 Premature contact of upper and lower teeth.
- 11. Instability of dentures due to their excessive height
- 12. Clicking of teeth in speech and mastication.

13. Separated upper and lower lip with poor esthetic and difficulty in bilabial sound (/p/b/m/).

- 14. Seem unable to open the mouth widely
- 15. Excessive display of artificial teeth and gum.



# **Consequences of Decreased vertical dimension:**

- 1. Comparatively lesser trauma to the denture bearing area.
- 2. Inharmony facial proportion (decreased lower facial height).
- 3. Difficulty in swallowing and speech.
- 4. Pain and clicking in the TMJ and muscular fatigue.


5. Loss of muscle tone and presence of wrinkles and folds that is not due to age.

- 6. Decreased space oral cavity and pushing the tongue back.
- 7. Loss of biting power.
- 8. Naso-labial angle is less than  $90^{\circ}$ .
- 9. Angular chelitis due to folding of the corner of the mouth.
- 10. Cheek biting.
- 11. Thinning of the vermilion borders of the lip
- 12. Prominence of lower jaw and chin

13. Obstruction of the opening of the Eustachian tube due to elevation of the soft palate due to elevation of the tongue and mandible.

### Prosthodontic

دبهاء الانصاري



The differences between increased and decreased vertical dimension.

#### Prosthodontic

### Methods of recording rest vertical dimension:

#### (Indirect methods to find occlusal vertical dimension)

1- Facial measurements: Instruct the patient to stand or sit comfortably upright with eyes looking straight ahead at some object which is on the same level. Insert the maxillary record base with the attached contoured occlusion rim. With an indelible marker, place a point of reference on the end of the patient's nose and another on the point of the chin. The patient is asked to perform functional movements like wetting his lips and swallowing, and to relax his shoulders (this is done to relax the supra- and infrahyoid muscles). When the mandible drops to the rest position, the distance between the points of reference is measured. Repeat this procedure until the measurements are consistent. Such measurements are helpful but cannot be considered as absolute.

**2- Tactile sense:** Instruct the patient to stand or sit erect and open the jaws wide until strain is felt in the muscles. When this opening becomes uncomfortable, ask them to close slowly until the jaws reach a comfortable, relaxed position. Measure the distance between the points of reference.



#### Prosthodontic


**3- Phonetics:** Ask the patient to repeat pronounce the letter m a certain numbers of times, like repeat the name *Emma* until they are aware of the contacting of the lips as the first syllabus *em* is pronounced. When patient have rehearsed this procedure, ask that they stop all jaw movement when the lips touch. At this time measure between the two points of reference.




**4- Facial expression:** The experienced dentist may notice the relaxed facial expression when the patient's jaws are at rest.

The following facial features indicate that the jaw is in its physiological rest position: The upper and lower lips should be even anteroposteriorly and in slight contact in a single plane. The skin around the eyes and over the chin should be relaxed; it should not be stretched, shiny, or excessively wrinkled. The nostrils are relaxed and breathing should be unobstructed. These evidences of rest position of the maxillomandibular musculature are the indications for recording a measurement of the vertical dimension of rest.


**5- Anatomical landmarks (Willis method):** The Willis guide is designed to measure the distance from the pupils of the eyes to the corner of the mouth and the distance from the anterior nasal spine to the lower border of the mandible. When these measurements are equal, the jaws are considered at rest. Its accuracy is questionable in patients with facial asymmetry.





Willis method and Boley gauge used to measure the distance recorded by Willis gauge.

**6- Electromyographic method (EMG):** By using a special device that measures the tone of masticatory muscles, when the tone is at its least, this means these muscles are in rest position and the jaws are at rest position.



Methods of recording occlusal vertical dimension:

(Direct methods to find occlusal vertical dimension)


**A. Pre-extraction records:** These records are made before the patient extracts all teeth and loses his occlusal vertical dimension; these records are:

**1. Profile photographs:** They are made and enlarged to life size. Measurements of anatomic landmarks on the photograph are compared with measurements using the same anatomic landmarks on the face. These measurements can be compared when the records are made and again when the artificial teeth are tried in. The photographs should be made with the teeth in maximum occlusion, as this position can




be maintained accurately for photographic procedures.

**2- Profile silhouettes:** An accurate reproduction of the profile silhouettes can be cut out in cardboard or contoured in wire. The silhouettes can be repositioned to the face after the vertical dimension has been established at the initial recording and/or when the artificial teeth are tried in.



**3- Profile radiographs:** They have been much used in researches of vertical dimension of occlusion rather than routine clinical use in prosthodontic treatment for edentulous patients. The two types of radiographs advocated are the cephalometric profile radiograph and radiograph of the condyles in the fossae. The inaccuracies that exist in either the technique or the method of comparing measurements make this method unreliable.




Articulated casts

#### Prosthodontic

**4- Articulated casts:** When the patient is dentulous, an accurate casts of the maxillary and mandibular arches have been made, the maxillary cast is related in its correct anatomic position on the articulator with a face-bow transfer. An occlusal record with the jaws in centric relation is used to mount the mandibular cast. After the teeth have been removed and edentulous casts have been mounted on the articulator, the interarch measurements are compared. Generally, the edentulous ridges will be parallel to one another at the correct vertical dimension of occlusion. This method is valuable with patients whose ridges are not sacrificed during the removal of the teeth or resorbed during a long waiting period for denture construction.

**5- Facial measurements:** Before extraction, the patient is instructed to close the jaws into maximum occlusion, then two tattoo points have been marked, one on the upper half of the face and the other on the lower half. The distance is measured, after extraction these measurements are compared with measurements made between these points when the artificial teeth are tried in.

6. Measurements from former dentures: Dentures that the patient has been wearing can be measured, and measurements can be correlated with observations of the patient's face to determine the amount of change required. These measurements are made between the ridge crests in the maxillary and mandibular dentures with a *Boley gauge*.





### **B.** Without Pre-extraction records:

### **1.** Boos power point method: By: Boos R.H.


A metal plate (*central bearing plate*) is attached to the maxillary record base. A bimeter (*an oral meter that measures pressure*) is attached to the mandibular record base. This bimeter has a dial, which shows the amount of pressure acting on it.

The record bases are inserted into the patient's mouth and the patient is asked to bite on the record bases at different degrees of jaw separation. The biting forces are transferred from the central bearing point to the bimeter. The highest value is called the power point which represents the occlusal vertical dimension.






# Lecture 10 Prosthodontic د.بهاء الاتصاري 2. Tactile sense or neuromuscular perception: A central bearing screw/central bearing plate apparatus is used and attached to accurately adapt record bases permits the patient to experience through neuromuscular perception the different vertical relations. The central bearing screw is adjusted downward and upward until the height of contact feels right to the patient and this represents the occlusal vertical dimension.




# 3. Swallowing threshold:

The theory behind this method is that at the beginning of swallowing cycle, the teeth of the upper and lower jaws almost come together with a very light contact. This factor can be used as a guide to determine the occlusal vertical dimension.

The technique involves fabrication of cones of soft wax on the mandibular record base. The maxillary and mandibular record bases are inserted in the patient mouth. Salivation is stimulated and the patient is asked to swallow. The repeated action of swallowing the saliva will gradually reduce the height of the wax cones to allow the mandible to reach the level of occlusal vertical dimension.





### 4. Phonetics: By: Silverman M. Meyer

Silverman's closest speaking space: It is the minimal amount of interocclusal space between the upper and lower teeth when sounds like ch, s, and j are pronounced. There is 1-2 mm clearance between teeth when observed from the profile and frontal view. Phonetic tests of the vertical dimension include listening to speech sound production and observing the relationships of teeth during speech. The production of ch, s, and j sounds brings the anterior teeth closest together without contact.

\* If the distance is too large, it means that too small a vertical dimension of occlusion may have been established.

\* If the anterior teeth touch when these sounds are made, the vertical dimension is probably too great.

