

**Al-Mustaqbal University**  
**College of sciences**  
**Department of Biology**



# ***Bio Physics***

## ***third lecture***

**M. Sc. Baraa Abd Alrda**

***First Stage***

***2024- 2023***

## Cross multiplication


Coordinate systems is an artificial mathematical tool that used to describe the position of an object in space.. There are three coordinate systems:

1. One dimension coordinate system (1D).
2. Two dimension coordinate system (2D).
3. Three dimension coordinate system (3D).

### (1D) Coordinate system

The easiest coordinate system use to describe the location of objects in one dimensional space. For example, to describe the location of a train along a straight section of track that runs in the East-West direction.

Fig (1).



**Figure (1): A 1D coordinate system describing the position of a train.**


In order to fully specify a one-dimensional coordinate system we need to choose:

- The location of the origin.
- The direction in which the coordinate,  $x$ , increases.
- The units in which we wish to express  $x$ .

In one dimension, it is common to use the variable  $x$  to define the position along the “ $x$ -axis”. The  $x$ -axis is our coordinate system in one dimension.


## 2D Coordinate systems

To describe the position of an object in two dimensions, we need to specify two numbers. The easiest way to do this is to define two axes,  $x$  and  $y$ . Fig (2) shows an example of such a coordinate system. The axes are perpendicular in “**Cartesian**” coordinate system.



**Figure (2): Example of Cartesian coordinate system and a point P with coordinates  $(x_p, y_p)$ .**

Another common choice is a “polar” coordinate system, where the position of an object is specified by a distance to the origin,  $r$ , and an angle  $\theta$ , relative to a specified direction, as shown in Fig (3). Often, a polar coordinate system is defined alongside a Cartesian system, so that  $r$  is the distance to the origin of the Cartesian system and  $\theta$  is the angle with respect to the axis.



**Fig (3): Example of a polar coordinate system and a point P with coordinates  $(r, \theta)$ .**


One can easily convert between the two Cartesian coordinates,  $x$  and  $y$ , and the two corresponding polar coordinates,  $r$  and  $\theta$ :

$$\begin{aligned}x &= r \cos(\theta) \\y &= r \sin(\theta) \\r &= \sqrt{x^2 + y^2} \\ \tan(\theta) &= \frac{y}{x}\end{aligned}$$

Polar coordinates are often used to describe the motion of an object moving around a circle, as this means that only one of the coordinates ( $\theta$ ) changes with time.

### **3D Coordinate systems**

In three dimensions, we need to specify three numbers to describe the position of an object. In a three dimensional Cartesian coordinate system, we simply add a third axis,  $z$ , that is mutually perpendicular to both  $x$  and  $y$ . The position of an object can then be specified by using the three coordinates  $x$ ,  $y$ , and  $z$ . Two additional coordinate systems are common in three dimensions: “cylindrical” and “spherical” coordinates. All three systems are illustrated in Fig (4) superimposed onto the Cartesian system.



**Figure (4): Cartesian (left), cylindrical (center) and spherical (right) coordinate systems used in three dimensions.**

**Cylindrical coordinates** can be thought of as an extension of the polar coordinates. We keep the same Cartesian coordinate  $z$  to indicate the height above the  $x$ - $y$  plane, however, we use the azimuthal angle,  $\phi$ , and the radius,  $\rho$ , to describe the position of the projection of a point onto the  $x$ - $y$  plane.  $\phi$  is the angle between the  $x$  axis and the line from the origin to the projection of the point in the  $x$ - $y$  plane and  $\rho$  is the distance between the point and the  $z$  axis.

The cylindrical coordinates are related to the Cartesian coordinates by:

$$\begin{aligned}\rho &= \sqrt{x^2 + y^2} \\ \tan(\phi) &= \frac{y}{x} \\ z &= z\end{aligned}$$

In **spherical coordinates**, a point  $P$  is described by the radius,  $r$ , the polar angle  $\theta$ , and the azimuthal angle  $\phi$ . The radius is the distance between the point and the origin. The polar angle is the angle with the  $z$  axis that is made by the line from the origin to the point. The azimuthal angle is defined in the same way as in polar coordinates.

\*\*The spherical coordinates are related to the Cartesian coordinates by:

$$\begin{aligned}r &= \sqrt{x^2 + y^2 + z^2} \\ \cos(\theta) &= \frac{z}{r} = \frac{z}{\sqrt{x^2 + y^2 + z^2}} \\ \tan(\phi) &= \frac{y}{x}\end{aligned}$$

Q1/ Convert (x, y, z) to polar coordinates where  $x=5$ ,  $y=4$ , and  $z=9$

## Velocity and Acceleration in Plane Polar Coordinates

Let the polar coordinates  $r$ ,  $\theta$  to express the position of a particle moving in a plane. The position of the particle can be written as the product of the radial distance  $r$  by a unit radial vector  $e_r$ :




Fig (7):Unit vectors for plane polar coordinates.

As the particle moves, both  $r$  and  $e_r$  vary; thus, they are both functions of the time. Hence, if we differentiate with respect to  $t$ .

$$\mathbf{v} = \frac{d\mathbf{r}}{dt} = \dot{r}\mathbf{e}_r + r\frac{d\mathbf{e}_r}{dt}$$

By using Equation for the derivative of the unit radial vector, we can finally write the equation for the velocity as:

$$\mathbf{v} = \dot{r}\mathbf{e}_r + r\dot{\theta}\mathbf{e}_\theta$$

Thus,  $\dot{r}$  is the radial component of the velocity vector, and  $r\dot{\theta}$  is the transverse component.

The equation for the acceleration vector in plane polar coordinates.

$$\mathbf{a} = (\ddot{r} - r\dot{\theta}^2)\mathbf{e}_r + (r\ddot{\theta} + 2\dot{r}\dot{\theta})\mathbf{e}_\theta$$

The radial component of the acceleration vector is:

$$a_r = \ddot{r} - r\dot{\theta}^2$$

And the transverse component is:

$$a_\theta = r\ddot{\theta} + 2\dot{r}\dot{\theta}$$

**Example [1]:** A body moves in a spiral path in such a way that the radial distance decreases at a constant rate  $r = b - ct$  while the angular speed increases at a constant rate,  $\dot{\theta} = kt$ , Find the speed as a function of time. By using equation of velocity.

$$\mathbf{v} = \dot{r}\mathbf{e}_r + r\dot{\theta}\mathbf{e}_\theta$$

We have  $\dot{r} = -c$  and  $\ddot{r} = 0$ .

$$\mathbf{v} = -c\mathbf{e}_r + (b - ct)kte_\theta$$

$$v = [c^2 + (b - ct)^2k^2t^2]^{1/2}$$

which is valid for  $t \leq b/c$ . Note that  $v = c$  both for  $t = 0, r = b$  and for  $t = b/c, r = 0$

**Example [2]:** A particle is moving along a spiral path with its polar coordinate position  $r = bt^2$  and  $\theta = ct$  where  $b$  and  $c$  is constant find the velocity and acceleration as a function of time. By using equation of velocity.

$$\mathbf{v} = \dot{r}\mathbf{e}_r + r\dot{\theta}\mathbf{e}_\theta$$

$$\begin{aligned} \mathbf{v} &= \mathbf{e}_r \frac{d}{dt} (bt^2) + \mathbf{e}_\theta (bt^2) \frac{d}{dt} (ct) \\ &= (2bt)\mathbf{e}_r + (bct^2)\mathbf{e}_\theta \end{aligned}$$

By using the equation of acceleration

$$\mathbf{a} = (\ddot{r} - r\dot{\theta}^2)\mathbf{e}_r + (r\ddot{\theta} + 2\dot{r}\dot{\theta})\mathbf{e}_\theta$$

$$\begin{aligned} \mathbf{a} &= \mathbf{e}_r(2b - bt^2c^2) + \mathbf{e}_\theta[0 + 2(2bt)c] \\ &= b(2 - t^2c^2)\mathbf{e}_r + 4bct\mathbf{e}_\theta \end{aligned}$$

## Velocity and Acceleration in Cylindrical Coordinates

In the case of three-dimensional motion, the position of a particle can be described in cylindrical coordinates  $R$ ,  $\phi$ ,  $z$ . The position vector is then written as:

$$\mathbf{r} = R\mathbf{e}_R + z\mathbf{e}_z$$

Where  $\mathbf{e}_R$  is a unit radial vector in the x-y plane and  $\mathbf{e}_z$  is the unit vector in the z direction. A third unit vector  $\mathbf{e}_\phi$  is needed so that the three vectors  $\mathbf{e}_R$ ,  $\mathbf{e}_\phi$ ,  $\mathbf{e}_z$  constitute a right-handed triad,

$$\mathbf{v} = \dot{R}\mathbf{e}_R + R\dot{\phi}\mathbf{e}_\phi + \dot{z}\mathbf{e}_z$$

$$\mathbf{a} = (\ddot{R} - R\dot{\phi}^2)\mathbf{e}_R + (2\dot{R}\dot{\phi} + R\ddot{\phi})\mathbf{e}_\phi + \ddot{z}\mathbf{e}_z$$

### *Example [3]:*

A bead slides on a wire bent into the form of a helix, the motion of the bead being given in cylindrical coordinates by  $R = b$ ,  $\phi = \omega t$ ,  $z = ct$ . Find the velocity and acceleration vectors as functions of time.

$$\text{we find } \dot{R} = \ddot{R} = 0, \dot{\phi} = \omega, \ddot{\phi} = 0, \dot{z} = c, \ddot{z} = 0.$$

By using the equation of velocity and acceleration

$$\mathbf{v} = b\omega\mathbf{e}_\phi + c\mathbf{e}_z$$
$$\mathbf{a} = -b\omega^2\mathbf{e}_R$$